

---

# **CUDRDC Sensor Project Documentation**

***Release 0.1.0***

**Jason Gao**

**Jul 12, 2019**

CONTENTS

1 About project 1

1.1 Radar Information . . . . . 1

1.2 Linux setup . . . . . 3

1.3 X4 Radar . . . . . 3

1.4 TI parser code . . . . . 7

1.5 Lidar Extraction Tool . . . . . 7

1.6 Ouster OS1 Lidar . . . . . 15

1.7 Test file . . . . . 17

Python Module Index 19

## ABOUT PROJECT

This project is funded by both the Defense Research and Development Canada (DRDC) and the National Research Council (NRC). These organizations are working alongside Carleton University students to develop a pip installable library that contains all the parsers used to convert radar and lidar data to readable csv files. The library also contains methods for determining radar thresholds. The radars used in this project are the Novelda X4M03, X4M300, X4M200 and the TSW1400. The lidar used is the Ouster OS1-16.

Contents:

## 1.1 Radar Information

### 1.1.1 Novelda X4

The X4 radars are IR-UWB and can work at frequencies ranging from 6 GHz to 10.2 GHz. The total number of bins that can be sampled is 1536.

#### Specifications

##### X4M300 Specs

- Detection Time: 1.5 - 3.0 seconds
- Range: 9.4 meters
- Antenna: Tx for transmission and Rx for receiving
- Baseband data output: 17 baseband/ssecond
- System on chip: Novelda UWB X4

##### X4M200 Specs

- Detection Time: 3.0 - 5.0 seconds
- Range: 5 meters
- Antenna: Tx for transmission and Rx for receiving
- Baseband data output: 17 baseband/ssecond
- System on chip: Novelda UWB X4

### Configuring X4 radar

1. Begin by initializing to default values using prebuilt function `x4driver_init()`
2. Set PRF using function `x4driver_set_prf_div(...)`

---

**Note:** The common PLL value of 243 MHz is divided by the arguemnent passed in to `x4driver_set_prf_div(...)` to get a PRF value

---

---

**Note:** Make sure that when changing the PRF that frame length is shorter than 1/PRF and avoid sampling previous pulse when transmitting next pulse.

---

3. Set DAC sweep range minimum and maximum using `x4driver_set_dac_min()` and `x4driver_set_dac_max()`
4. Set 0 reference using `x4driver_set_frame_area_offset()`
5. Set frame area using function `x4driver_set_frame_area()` that takes two arguements, one for start of frame and one for end of frame.

### Setting radar FPS

To set the radar FPS the following parameters are required, PRF, iterations, pulse per step, dac max and dac min range as well as duty cycle.

$$FPS = \frac{PRF}{iteration * pulse_{per\_step} * (dac_{max} - dac_{min} + 1)} * duty_{cycle}$$

Our Novelda radar is configured to a FPS of 17 pulse/second so if you wanted to change FPS then the above parameter would need to be changed.

---

**Note:** The resulting FPS can be read using the built-in function `x4driver_get_fps()`.

---

### Example pulse\_per\_step calculation

- PRF: 16 MHz
- X4\_duty\_cycle: 95%
- dac\_max: 1100
- dac\_min: 949
- iteration: 64
- FPS: 17

$$\begin{aligned} pulse_{per\_step} &= \frac{PRF}{iteration * FPS * (dac_{max} - dac_{min} + 1)} * D \\ pulse_{per\_step} &= \frac{16MHz}{64 * 17 * 150} * 0.95 \\ pulse_{per\_step} &= 87 \end{aligned}$$

### 1.1.2 TSW1400

The TSW1400 board is used to interface with TI radars.

#### Specifications

- Operates using 5 V power source and is controlled by the SW7 switch.
- 11 LEDS used to indicate presence of power and state of FPGA.
- Control of the TSW1400 is via USB cable to a Windows PC.

Refer to [TSW1400 Comprehensive Guide](#) for full guide on hardware and software installations

#### Required softwares

[mmWaveSDK](#)

[mmWaveDFP](#)

[High speed data converter](#)

[MATLAB runtime engine](#)

---

**Note:** If you don't have Code Composer Studio v7.1 or higher installed get:

---

[XDS Emulation Software Package](#)

## 1.2 Linux setup

To install Linux with Ubuntu v18.04 on a Windows PC, users must install the following files:

[VirtualBox Software](#)

[Ubuntu 18.04 download](#)

[Quick tutorial on installing Ubuntu](#)

### 1.2.1 Quick tips for linux beginners

- Set the network setting to use bridged adapter so Linux doesn't share the same ip address as your Windows PC.
- Insert guest addition CD image found in the *Devices* tab for auto-adjusted screen resolutions.
- Use `~/` to `cd` from home directory

## 1.3 X4 Radar

### 1.3.1 Parser for iq data

`x4_parser.iq_data(filename, csvname)`

Reads in a binary file and data from range bins is taken and complex iq data is stored in a csv file specified by csvname.

Parameter:

**filename: str** The .dat binary file name.

**csvname: str** User defined .csv file name

Example:

```
>>> iq_data('X4data.dat', 'X4iq_data')
>>> 'converted'
```

Returns:

Readable csv file containing complex values.

### 1.3.2 Parser for raw data

`X4_parser.raw_data(filename, csvname)`

Reads in a binary file and data from range bins is taken and raw data is stored in a csv file specified by csvname.

Parameters:

**filename: str** The .dat binary file name.

**csvname: str** User defined .csv file name

Example:

```
>>> raw_data('X4data.dat', 'X4raw_data')
>>> 'converted'
```

Returns:

Readable csv files containing raw data.

### 1.3.3 X4 Record and playback code

Target module: X4M200,X4M300,X4M03

Introduction:

XeThru modules support both RF and baseband data output. This is an example of radar raw data manipulation. Developer can use Module Connector API to read, record radar raw data, and also playback recorded data.

Command to run: `python X4_record_playback.py -d com3-b -r`

- `-d com3` represents device name and can be found when starting Xethru Explorer.
- `-b` to use baseband to record, default is radio frequency.
- `-r` to start recording.

`X4_record_playback.clear_buffer(mc)`

Clears the frame buffer

Parameter:

**mc: object** module connector object

`X4_record_playback.main()`

Creates a parser with subcategories.

Return:

A simple XEP plot of live feed from X4 radar.

`X4_record_playback.on_file_available(data_type, filename)`

Returns the file name that is available after recording.

Parameters:

**data\_type: str** data type of the recording file.

**filename: str** file name of recording file.

`X4_record_playback.on_meta_file_available(session_id, meta_filename)`

Returns the meta file name that is available after recording.

Parameters:

**session\_id: str** unique id to identify meta file

**filename: str** file name of meta file.

`X4_record_playback.playback_recording(meta_filename, baseband=False)`

Plays back the recording.

Parameters:

**meta\_filename: str** Name of meta file.

**baseband: boolean** Check if recording with baseband iq data.

`X4_record_playback.reset(device_name)`

Resets the device profile and restarts the device

Parameter:

**device\_name: str** Identifies the device being used for recording using it's port number.

`X4_record_playback.simple_xep_plot(device_name, record=False, baseband=False)`

Plots the recorded data.

Parameters:

**device\_name: str** port that device is connected to.

**record: boolean** check if device is recording.

**baseband: boolean** check if recording with baseband iq data.

Return:

Simple plot of range bin by amplitude.

### 1.3.4 X4 Threshold detection

To use these functions first take the data recorded from the X4 radar and pass it into the `iq_data()` function found in `X4_parser.py` to get a complex csv file. The file received will be used wherever *filename* is an argument.

`X4_threshold.csv_into_list(filename)`

Converts data from a CSV file into a numpy array.

Data is collected from “XEP\_X4M200\_X4M300\_plot\_record\_playback.py”. Then .dat file is converted into a CSV file using the library.

Parameters:

**filename: str** Csv file name.

Example:

```
>>> csv_into_list("Helii50040.csv")
>>> array([[2.12019056e-04, 2.66481591e-04, 3.51781533e-04, ...,
2.51499279e-04, 2.63311858e-04, 2.49837321e-04],
[1.36839763e-03, 1.13654408e-03, 7.92290507e-04, ...,
3.49299137e-04, 1.30311682e-04, 1.87399805e-04],
[7.57068081e-04, 6.54611670e-04, 6.83445863e-04, ...,
6.95117789e-05, 2.17249015e-04, 3.85946482e-04],
...,
[9.57032957e-04, 5.99047943e-04, 5.37280418e-04, ...,
2.95999810e-04, 2.42217122e-04, 3.25605109e-04],
[2.37110777e-03, 1.98986895e-03, 1.28061167e-03, ...,
2.95363991e-04, 1.50057104e-04, 2.33757752e-04],
[6.45687293e-04, 5.61334516e-04, 1.63285784e-04, ...,
6.64671904e-05, 2.17249015e-04, 1.93614790e-04]])
```

Returns:

A numpy array of the data.

`X4_threshold.distance_finder(filename, estimate_threshold)`

Converts the positive range bin/bins to a given distance in centimetres for a target. Formula used for this is (bin)\*5.25-18. Each range bin is 5.25 cm and starting offset is 18 cm.

Parameters:

**filename: str** Csv file name.

**estimated\_threshold: float** Threshold to block out background noise.

Example:

```
>>> distance_finder("Helii50040.csv", 0.02)
>>> [29.25]
```

Returns:

List of ranges in centimetres where all the possible targets above the threshold are located.

`X4_threshold.noise_power_estimate(filename, estimated_threshold)`

Finds the noise power estimate.

Given the filename, the file is converted to an array. The average for the the array is taken excluding the points above the threshold and their respective guard cells. The noise power estimate is then found by subtracting the positive and guard cells from the overall sum. When the noise power estimate is multiplied by the threshold factor, the threshold can be found.

Parameters:

**filename: str** Csv file name.

**estimated\_threshold: float** Threshold to block out background noise.

Example:

```
>>> noise_power_estimate("Helii50040.csv", 0.02)
>>> 0.00045988029076158947
```

Returns:

A number representing the noise power estimate.

`X4_threshold.plot_data(filename)`

Plots the data array for the 5th sample set.



Parameters:

**filename: str** Csv file name.

Example:

```
>>> plot_data("Heli150040.csv")
```

Returns:

Graph showing the range bin with respect to their corresponding strength of signal.

`x4_threshold.range_finder(filename, estimated_threshold)`

Finds the range bin/bins from the radar data.

Given the filename, the file is converted to an array. The points above the given threshold are returned.

Parameters:

**filename: str** Csv file name

**estimated\_threshold: float** Threshold to block out background noise.

Example:

```
>>> range_finder("Heli150040.csv", 0.02)
>>> [9]
```

Returns:

A list of range bins that has signal strength values above the threshold.

## 1.4 TI parser code

`TI_parser.readTIdata(filename, csvname)`

Reads in a binary file and outputs the iq complex data to a csv file specified by csvname.

Parameter:

**filename: str** file name of binary file.

**csvname: str** csv file name that stores the iq data from binary file.

Example:

```
>>> readTIdata('TIdata.bin', 'TIdata')
>>> 'converted'
```

Return:

Readable csv file containing complex data.

## 1.5 Lidar Extraction Tool

The lidar extraction tool is used to extract relevant data from the `/os1_node/lidar_packets` and `/os1_node/imu_packets` topics that were created when recording using the Ouster OS1-16 lidar. From the `lidar_packets` topic, the tool can extract data such as global timestamps, lidar timestamps, range, number of signal photons, etc. From the `imu_packets` topic, the tool can extract data such as global timestamp, IMU timestamp, acceleration in xyz and angular velocity in the xyz plane. The tool uses a GUI interface so that navigating it is simple.

This GUI tool also calculate the xyz cartesian coordinates using lidar packet data and fit it to a lidar coordinate frame.

## 1.5.1 Functions

### Lidar packet functions

The below functions are used to read certain data categories as mentioned above from a csv file to the user through the use of the GUI interface.

```
lidar_extract.get_encoder_count (data,      arg,      single_row=False,      multiple_row=False,  
                                row_section=False)
```

Returns the encoder count of the csv file made from the lidar recording. Based on what boolean the user set to be true, the encoder count will output for those row(s).

Parameters:

**data: Pandas dataframe** A pandas dataframe used to extract values.

**arg: int** The row(s) number to be read.

**single\_row: boolean** If this is set to true, output the encoder count for the row that the user selected.

**multiple\_row: boolean** If this is set to true, output the encoder count for the rows that the user selected.

**row\_section: boolean** If this is set to true, output the encoder count for the row sections the user selected.

Return:

An array of all the encoder count the user desired to read.

```
lidar_extract.get_frame_id (data,      arg,      single_row=False,      multiple_row=False,  
                             row_section=False)
```

Returns the frame ID of the csv file made from the lidar recording. Based on what boolean the user set to be true, the frame ID will output for those row(s).

Parameters:

**data: Pandas dataframe** A pandas dataframe used to extract values.

**arg: int** The row(s) number to be read.

**single\_row: boolean** If this is set to true, output the frame IDs for the row that the user selected.

**multiple\_row: boolean** If this is set to true, output the frame IDs for the rows that the user selected.

**row\_section: boolean** If this is set to true, output the frame IDs for the row sections the user selected.

Return:

An array of all the frame IDs the user desired to read.

```
lidar_extract.get_measurement_id (data,      arg,      single_row=False,      multiple_row=False,  
                                  row_section=False)
```

Returns the measurement ID of the csv file made from the lidar recording. Based on what boolean the user set to be true, the measurement ID will output for those row(s).

Parameters:

**data: Pandas dataframe** A pandas dataframe used to extract values.

**arg: int** The row(s) number to be read.

**single\_row: boolean** If this is set to true, output the measurement IDs for the row that the user selected.

**multiple\_row: boolean** If this is set to true, output the measurement IDs for the rows that the user selected.

**row\_section: boolean** If this is set to true, output the measurement IDs for the row sections the user selected.

Return:

An array of all the measurement IDs the user desired to read.

```
lidar_extract.get_noise_photons(data, arg, single_row=False, multiple_row=False,
                                row_section=False, azimuth_block=0)
```

Returns the noise photons of the csv file made from the lidar recording. Based on what boolean the user set to be true, the noise photons will output for those row(s).

Parameters:

**data: Pandas dataframe** A pandas dataframe used to extract values.

**arg: int** The row(s) number to be read.

**azimuth\_block: int** Specifies which azimuth to read noise photons values from.

**single\_row: boolean** If this is set to true, output the noise photons for the row that the user selected.

**multiple\_row: boolean** If this is set to true, output the noise photons for the rows that the user selected.

**row\_section: boolean** If this is set to true, output the noise photons for the row sections the user selected.

Return:

An array of all the noise photons the user desired to read.

```
lidar_extract.get_range(data, arg, single_row=False, multiple_row=False, row_section=False, azimuth_block=0)
```

Returns the range of the csv file made from the lidar recording. Based on what boolean the user set to be true, the range will output for those row(s).

Parameters:

**data: Pandas dataframe** A pandas dataframe used to extract values.

**arg: int** The row(s) number to be read.

**azimuth\_block: int** Specifies which azimuth to read range values from.

**single\_row: boolean** If this is set to true, output the range for the row that the user selected.

**multiple\_row: boolean** If this is set to true, output the range for the rows that the user selected.

**row\_section: boolean** If this is set to true, output the erange for the row sections the user selected.

Return:

An array of all the range the user desired to read.

```
lidar_extract.get_reflectivity(data, arg, single_row=False, multiple_row=False,
                                row_section=False, azimuth_block=0)
```

Returns the reflectivity of the csv file made from the lidar recording. Based on what boolean the user set to be true, the reflectivity will output for those row(s).

Parameters:

**data: Pandas dataframe** A pandas dataframe used to extract values.

**arg: int** The row(s) number to be read.

**azimuth\_block: int** Specifies which azimuth to read reflectivity values from.

**single\_row: boolean** If this is set to true, output the reflectivity for the row that the user selected.

**multiple\_row: boolean** If this is set to true, output the reflectivity for the rows that the user selected.

**row\_section: boolean** If this is set to true, output the reflectivity for the row sections the user selected.

Return:

An array of all the reflectivity the user desired to read.

```
lidar_extract.get_signal_photons (data, arg, single_row=False, multiple_row=False,  
                                row_section=False, azimuth_block=0)
```

Returns the signal photons of the csv file made from the lidar recording. Based on what boolean the user set to be true, the signal photons will output for those row(s).

Parameters:

**azimuth\_block: int** Specifies which azimuth to read signal photons values from.

**single\_row: boolean** If this is set to true, output the signal photons for the row that the user selected.

**multiple\_row: boolean** If this is set to true, output the signal photons for the rows that the user selected.

**row\_section: boolean** If this is set to true, output the signal photons for the row sections the user selected.

Return:

An array of all the signal photons the user desired to read.

```
lidar_extract.get_timestamp (data, arg, single_row=False, multiple_row=False,  
                             row_section=False)
```

Returns the timestamp of the csv file made from the lidar recording. Based on what boolean the user set to be true, the timestamp will output for those row(s).

Parameters:

**data: Pandas dataframe** A pandas dataframe used to extract values.

**arg: int** The row(s) number to be read.

**single\_row: boolean** If this is set to true, output the timestamps for the row that the user selected.

**multiple\_row: boolean** If this is set to true, output the timestamps for the rows that the user selected.

**row\_section: boolean** If this is set to true, output the timestamps for the row sections the user selected.

Return:

An array of all the timestamps the user desired to read.

## IMU packet functions

The below functions are used to read certain data categories as mentioned above from a csv file to the user through the use of the GUI interface.

`imu_extract.get_IMU_time (data, arg, single_row=False, multiple_row=False, row_section=False)`

Takes in a file and row argument(s) along with a boolean that specifies the amount of rows to read the IMU timestamps for.

Parameter:

**data: file** The csv file that is passed in to read.

**arg: int** The row(s) that are to be read.

**single\_row: boolean** If chosen the IMU timestamp for a single row specified by arg will be output.

**multiple\_row: boolean** If chosen the IMU timestamp for multiple rows specified by arg will be output.

**row\_section: boolean** If chosen the IMU timestamp for a row section by arg will be output.

Return:

An array of IMU timestamps.

`imu_extract.get_accel_time (data, arg, single_row=False, multiple_row=False, row_section=False)`

Takes in a file and row argument(s) along with a boolean that specifies the amount of rows to read the accelerometer timestamps for.

Parameter:

**data: file** The csv file that is passed in to read.

**arg: int** The row(s) that are to be read.

**single\_row: boolean** If chosen the accelerometer timestamp for a single row specified by arg will be output.

**multiple\_row: boolean** If chosen the accelerometer timestamp for multiple rows specified by arg will be output.

**row\_section: boolean** If chosen the accelerometer timestamp for a row section by arg will be output.

Return:

An array of accelerometer timestamps.

`imu_extract.get_gyro_time (data, arg, single_row=False, multiple_row=False, row_section=False)`

Takes in a file and row argument(s) along with a boolean that specifies the amount of rows to read the gyroscope timestamps for.

Parameter:

**data: file** The csv file that is passed in to read.

**arg: int** The row(s) that are to be read.

**single\_row: boolean** If chosen the gyroscope timestamp for a single row specified by arg will be output.

**multiple\_row: boolean** If chosen the gyroscope timestamp for multiple rows specified by arg will be output.

**row\_section: boolean** If chosen the gyroscope timestamp for a row section by arg will be output.

Return:

An array of gyroscope timestamps.

`imu_extract.get_x_accel (data, arg, single_row=False, multiple_row=False, row_section=False)`

Takes in a file and row argument(s) along with a boolean that specifies the amount of rows to read the x acceleration for.

Parameter:

**data: file** The csv file that is passed in to read.

**arg: int** The row(s) that are to be read.

**single\_row: boolean** If chosen the x acceleration for a single row specified by arg will be output.

**multiple\_row: boolean** If chosen the x acceleration for multiple rows specified by arg will be output.

**row\_section: boolean** If chosen the x acceleration for a row section by arg will be output.

Return:

An array of x acceleration.

`imu_extract.get_x_ang_vel (data, arg, single_row=False, multiple_row=False, row_section=False)`

Takes in a file and row argument(s) along with a boolean that specifies the amount of rows to read the x angular velocity for.

Parameter:

**data: file** The csv file that is passed in to read.

**arg: int** The row(s) that are to be read.

**single\_row: boolean** If chosen the x angular velocity for a single row specified by arg will be output.

**multiple\_row: boolean** If chosen the x angular velocity for multiple rows specified by arg will be output.

**row\_section: boolean** If chosen the x angular velocity for a row section by arg will be output.

Return:

An array of x angular velocity.

`imu_extract.get_y_accel (data, arg, single_row=False, multiple_row=False, row_section=False)`

Takes in a file and row argument(s) along with a boolean that specifies the amount of rows to read the y acceleration for.

Parameter:

**data: file** The csv file that is passed in to read.

**arg: int** The row(s) that are to be read.

**single\_row: boolean** If chosen the y acceleration for a single row specified by arg will be output.

**multiple\_row: boolean** If chosen the y acceleration for multiple rows specified by arg will be output.

**row\_section: boolean** If chosen the y acceleration for a row section by arg will be output.

Return:

An array of y acceleration.

`imu_extract.get_y_ang_vel (data, arg, single_row=False, multiple_row=False, row_section=False)`

Takes in a file and row argument(s) along with a boolean that specifies the amount of rows to read the y angular velocity for.

Parameter:

**data: file** The csv file that is passed in to read.

**arg: int** The row(s) that are to be read.

**single\_row: boolean** If chosen the y angular velocity for a single row specified by arg will be output.

**multiple\_row: boolean** If chosen the y angular velocity for multiple rows specified by arg will be output.

**row\_section: boolean** If chosen the y angular velocity for a row section by arg will be output.

Return:

An array of y angular velocity.

`imu_extract.get_z_accel(data, arg, single_row=False, multiple_row=False, row_section=False)`

Takes in a file and row argument(s) along with a boolean that specifies the amount of rows to read the z acceleration for.

Parameter:

**data: file** The csv file that is passed in to read.

**arg: int** The row(s) that are to be read.

**single\_row: boolean** If chosen the z acceleration for a single row specified by arg will be output.

**multiple\_row: boolean** If chosen the z acceleration for multiple rows specified by arg will be output.

**row\_section: boolean** If chosen the z acceleration for a row section by arg will be output.

Return:

An array of z acceleration.

`imu_extract.get_z_ang_vel(data, arg, single_row=False, multiple_row=False, row_section=False)`

Takes in a file and row argument(s) along with a boolean that specifies the amount of rows to read the z angular velocity for.

Parameter:

**data: file** The csv file that is passed in to read.

**arg: int** The row(s) that are to be read.

**single\_row: boolean** If chosen the z angular velocity for a single row specified by arg will be output.

**multiple\_row: boolean** If chosen the z angular velocity for multiple rows specified by arg will be output.

**row\_section: boolean** If chosen the z angular velocity for a row section by arg will be output.

Return:

An array of z angular velocity.

## XYZ Coordinate functions

The below functions are used to calculate xyz cartesian points onto a lidar coordinate frame using data extracted from the lidar packets

### Lidar Extraction Tool GUI

To run this tool make sure to read the instructions for a quick simple how-to guide. Functions can be found here

`test_lidar_gui.command(entry)`

Takes in a number of rows to be read from file and maps to list of ints.

Parameters:

**entry: int** The row numbers that will be output.

Return:

mapped list of data

`test_lidar_gui.imu_multiple_row()`

GUI window for reading IMU data of multiple rows

Return:

A textbox of the parameter data user wanted to read.

`test_lidar_gui.imu_row_section()`

GUI window for reading IMU data of the row section

Return:

A textbox of the parameter data user wanted to read.

`test_lidar_gui.imu_single_row()`

GUI window for reading IMU data of the single row

Return:

A textbox of the parameter data user wanted to read.

`test_lidar_gui.instruction()`

A set of instructions on how to use the program

`test_lidar_gui.lidar_multiple_row()`

GUI window for reading lidar data of multiple rows

Return:

A textbox of the parameter data user wanted to read.

`test_lidar_gui.lidar_row_section()`

GUI window for reading lidar data of the row section

Return:

A textbox of the parameter data user wanted to read.

`test_lidar_gui.lidar_single_row()`

GUI window for reading lidar data in a single row

Return:

A textbox of the parameter data user wanted to read.

`test_lidar_gui.openfile()`

Opens the csv file for reading lidar and IMU packet parameters.

`test_lidar_gui.print_list(lst)`

Takes in an array and prints it to textbox.

Parameters:



**lst: list** A list object of the data that will be read to user.

```
test_lidar_gui.xyz_calc()
```

GUI window for reading the xyz coordinates gotten from lines of the lidar csv file.

Return:

A textbox of the xyz coordinates from rows of the lidar csv file.

## 1.6 Ouster OS1 Lidar

### 1.6.1 Specs

*All below specs are for the OS1-16 lidar that was used in this project* - Works on channels 16, 64, 128. - Maximum range of 120 meters. - Field of view of 33.2 degree vertically and 360 degree horizontally. - Sampling rate of 327,680 points/second.

### 1.6.2 Setup lidar

1. Connect lidar interface box to router that supports Gigabit connection.
2. Connect lidar to lidar interface box via cable.
3. Determine the ip address your router gave the lidar when it connected to the network and jot it down.
4. Determine your linux ip adress by running *ifconfig* in terminal and jot it down.

### 1.6.3 Ouster Github

The following [Github page](#) provides information on how to view raw data streams, visualize data and use a robot operating system (ROS) to save recorded data in a .bag file. ROS commands can also replay data in .bag files and convert .bag files to .csv files.

---

**Note:** Some version of Linux running Ubuntu must be used. It is recommended to run Ubuntu 18.04 for best results. Follow instructions in *Ubuntu* page for more details on installing Linux with Ubuntu.

---

### Ouster client

The Ouster client allows users to see the raw data stream that the lidar is collecting and sending to the specified ip address. Instruction on building the client in Linux can be found here [Building client](#).

### Running client

1. `cd /path/to/ouster_client_example`
2. `type ./ouster_client_example <os1_hostname> <udp_dest_ip>`

**<os1\_hostname>** is the hostname/ip address of OS1-16 lidar.

**<udp\_data\_dest\_ip>** is the destination ip address the lidar sends data to. e.g. ip address from running *ifconfig*.

### Ouster visualization

The Ouster visualization is used for building a basic visualizer frame of collected lidar data. Instructions on building visualizer and it's dependencies can be found here [Building visualizer](#). The visualizer can be run in real time or with recorded data.

### Running visualizer

1. `cd /path/to/ouster_viz/build`
2. `./viz -m <frame_size> <os1_hostname> <udp_data_dest_ip>`

**<frame\_size>** is the size of the visualization frame and can ONLY be the following: 512x10, 512x20, 1024x10, 1024x20, 2048x10.

**<os1\_hostname>** is the ip address of lidar.

**<udp\_data\_ip\_dest>** is the ip address lidar sends data to.

### Ouster ROS

---

**Note:** For Ubuntu 18.04 users it is best to use **ROS Melodic** as **ROS Kinetic** (The ROS provided on the GitHub page) is only compatible with Ubuntu 16.04 and lower.

---

Building the ROS Node can be found here [Building ROS Kinetic](#).

For Ubuntu 16.04 users and lower: [Installation of ROS Kinetic](#)

For Ubuntu 18.04 users: [Installation of ROS Melodic](#)

For new users to using ROS: [ROS Tutorials](#)

### Running ROS Node

---

**Note:** Before typing any commands make sure to always source the `setup.bash` file in your created ROS workspace otherwise it will return a error. The file can be sourced with the command `source /path/to/myworkspace/devel/setup.bash`.

---

For recording lidar data:

1. `roslaunch ouster_ros os1.launch os1_hostname:=<os1_hostname> os1_udp_dest:=<os1_udp_dest> lidar_mode<:=<lidar_mode>`. The option to visualize live data can be turned on by adding `viz:=true` to the `roslaunch` command.

**<os1\_hostname>** is the ip address of the lidar

**<os1\_udp\_dest>** is the ip address the lidar sends data to

**<lidar\_mode>** is the size of the lidar visualization frame

2. `rosbag record -O <recorded__bag_filename> /os1_node/imu_packets /os1_node/lidar_packets` in a new terminal

`/os1_node/imu_packets` and `/os1_node/lidar_packets` are your topic names that the lidar sends messages to via the node you built. These topic names can be changed to user preference.

---

**Note:** DO NOT close the terminal with the `roslaunch` command open otherwise `rosbag` will crash.

---

For replaying lidar data:

1. `roslaunch ouster_ros os1.launch replay:=true os1_hostname:=<os1_hostname>`
2. In a **new** terminal run `rosbag play <bag_filename>`

---

**Note:** DO NOT close the terminal with the `roslaunch` command open otherwise `rosbag` will crash.

---

Converting data to csv file: Run `rostopic echo "topic name" -b "bag_filename" -p > filename.csv`

---

**Note:** To find topic names run the command `rosbag info <bag_filename>`

---

## 1.7 Test file

```
class test.TestParser (methodName='runTest')
```

```
    X4_Threshold_bin_to_distance ()
```

```
        Method to test if range bin to distance converted correctly
```

```
    X4_Threshold_noise_estimate ()
```

```
        Method to test if noise estimate was calculated properly
```

```
    X4_Threshold_range_finder ()
```

```
        Method to test if correct range bin was gotten from running function on csv file.
```

```
    test_TI ()
```

```
        Method to test if .bin binary file was converted successfully to .csv file with iq data put together.
```

```
    test_iq ()
```

```
        Method to test if .dat binary file was converted successfully to .csv file with in-phase and quadrature components together.
```

```
    test_raw ()
```

```
        Method to test if .dat binary file was converted successfully to .csv file with in-phase and quadrature component separated.
```

Novelda X4 binary file to complex or raw csv file

Novelda X4 data collection and playback

Novelda X4 threshold

TI binary file to complex csv file

Unit tests for radar parser and Novelda threshold calculator



## PYTHON MODULE INDEX

### i

`imu_extract`, 10

### l

`lidar_extract`, 8

### t

`test`, 17

`test_lidar_gui`, 14

`TI_parser`, 7

### X

`X4_parser`, 3

`X4_record_playback`, 4

`X4_threshold`, 5

`xyz_calc`, 13